

Error: Macro TranslatedPages(None) failed

expected string or buffer

ARexx Function List

1. ADDRDELETE
2. ADDREDIT
3. ADDRFIND
4. ADDRGOTO
5. ADDRINFO
6. ADDRLOAD
7. ADDRNEW
8. ADDRRESOLVE
9. ADDRSAVE
10. APPBUSY
11. APPNOBUSY
12. FINDMAIL
13. FLUSHINDEXES
14. FOLDERINFO
15. GETCONFIGINFO
16. GETFOLDERINFO
17. GETMAILINFO
18. GETSELECTED
19. GETURL
20. HELP
21. HIDE
22. INFO
23. ISONLINE
24. LISTFREEZE
25. LISTSELECT
26. LISTUNFREEZE
27. MAILARCHIVE
28. MAILBOUNCE
29. MAILCHANGESUBJECT
30. MAILCHECK
31. MAILCOPY
32. MAILDELETE
33. MAILEDIT
34. MAILEXPORT
35. MAILFILTER
36. MAILFORWARD
37. MAILIMPORT
38. MAILINFO
39. MAILMOVE
40. MAILREAD
41. MAILREPLY
42. MAILSEND
43. MAILSENDALL
44. MAILSTATUS
45. MAILUPDATE
46. MAILWRITE
47. NEWMAILFILE
48. QUIT

49. READCLOSE
50. READINFO
51. READPRINT
52. READSAVE
53. REQUEST
54. REQUESTFILE
55. REQUESTFOLDER
56. REQUESTSTRING
57. RESTART
58. SCREENTOBACK
59. SCREENTOFRONT
60. SETFLAG
61. SETFOLDER
62. SETMAIL
63. SETMAILFILE
64. SHOW
65. USERINFO
66. WRITEATTACH
67. WRITEBCC
68. WRITECC
69. WRITEEDITOR
70. WRITEFROM
71. WRITEIDENTITY
72. WRITELETTER
73. WRITEMAILTO
74. WRITEOPTIONS
75. WRITEQUEUE
76. WRITEREPLYTO
77. WRITESEND
78. WRITESUBJECT
79. WRITETO

FOLDERINFO

NAME

FolderInfo -- Return information about a folder. (V2.0)

TEMPLATE

VAR/K,STEM/K,FOLDER

FUNCTION

Returns information about the specified folder, or the current folder if none is specified.

INPUTS

VAR/K - variable where the results will be stored
 STEM/K - base name used for the stems where the returned data will be stored
 FOLDER - name or path of the folder we want to get info about; if no folder is specified, the current folder will be used (V2.2)

RETURNS

VAR - string with a space separated list of the results of the query
 <STEM>NUMBER - position of the folder in the folder list; the folder at the top is in slot 0
 <STEM>NAME - name of the folder as shown in the folder list

<STEM>PAT - path of the folder, e.g. "incoming"
<STEM>TOTAL - total number of messages in the folder
<STEM>NEW - number of new messages in the folder
<STEM>UNREAD - number of unread messages in the folder
<STEM>SIZE - size of the folder, in bytes
<STEM>TYPE - type of folder (V2.3), possible values are:
 ◇ 0 - normal
 ◇ 1 - incoming
 ◇ 2 - outgoing
 ◇ 3 - sent (for the default "Sent" folder)
 ◇ 4 - deleted
 ◇ 5 - sent and received
 ◇ 6 - sent

RC is set to 10 if the specified folder cannot be found.

NOTES

EXAMPLE

```
/* Enable result codes */
OPTIONS RESULTS

/* Request info */
FOLDERINFO 'Incoming' STEM fi.

/* Display results */
SAY 'Folder number:  'fi.number
SAY 'Folder name:   'fi.name
SAY 'Path:         'fi.path
SAY 'Total messages: 'fi.total
SAY 'New messages:  'fi.new
SAY 'Unread messages: 'fi.unread
SAY 'Total size:    'fi.size
SAY 'Type:         'fi.type
```

BUGS

SEE ALSO