

Error: Macro TranslatedPages(None) failed

expected string or buffer

ARexx Function List

1. ADDRDELETE
2. ADDREDIT
3. ADDRFIND
4. ADDRGOTO
5. ADDRINFO
6. ADDRLOAD
7. ADDRNEW
8. ADDRRESOLVE
9. ADDRSAVE
10. APPBUSY
11. APPNOBUSY
12. FINDMAIL
13. FLUSHINDEXES
14. FOLDERINFO
15. GETCONFIGINFO
16. GETFOLDERINFO
17. GETMAILINFO
18. GETSELECTED
19. GETURL
20. HELP
21. HIDE
22. INFO
23. ISONLINE
24. LISTFREEZE
25. LISTSELECT
26. LISTUNFREEZE
27. MAILARCHIVE
28. MAILBOUNCE
29. MAILCHANGESUBJECT
30. MAILCHECK
31. MAILCOPY
32. MAILDELETE
33. MAILEDIT
34. MAILEXPORT
35. MAILFILTER
36. MAILFORWARD
37. MAILIMPORT
38. MAILINFO
39. MAILMOVE
40. MAILREAD
41. MAILREPLY
42. MAILSEND
43. MAILSENDALL
44. MAILSTATUS
45. MAILUPDATE
46. MAILWRITE
47. NEWMAILFILE
48. QUIT

49. READCLOSE
50. READINFO
51. READPRINT
52. READSAVE
53. REQUEST
54. REQUESTFILE
55. REQUESTFOLDER
56. REQUESTSTRING
57. RESTART
58. SCREENTOBACK
59. SCREENTOFRONT
60. SETFLAG
61. SETFOLDER
62. SETMAIL
63. SETMAILFILE
64. SHOW
65. USERINFO
66. WRITEATTACH
67. WRITEBCC
68. WRITECC
69. WRITEEDITOR
70. WRITEFROM
71. WRITEIDENTITY
72. WRITELETTER
73. WRITEMAILTO
74. WRITEOPTIONS
75. WRITEQUEUE
76. WRITEREPLYTO
77. WRITESEND
78. WRITESUBJECT
79. WRITETO

READINFO

NAME

ReadInfo -- Return information about the attachments of the message in the active Read window. (V2.0)

TEMPLATE

VAR/K,STEM/K

FUNCTION

Returns information about the attachments of the message in the active Read window as set by MAILREAD?.

INPUTS

VAR/K - alternative variable to put the results into instead of RESULT
 STEM/K - base name used for the stems where the results will be stored

RETURNS

VAR - info returned by the query
 <STEM>FILENAME .COUNT - number of parts of the message, excluding the first header block
 <STEM>FILENAME .NR - filename of the nth part of the message, where nr is a number between 0 and n-1
 (0 = first part after the headers, usually the body of the message)

<STEM>FILETYPE.NR - content type of the nth part of the message, where nr is a number between 0 and n-1 (0 = first part after the headers, usually the body of the message)
<STEM>FILESIZE.NR - size of the nth part of the message, where nr is a number between 0 and n-1 (0 = first part after the headers, usually the body of the message)
<STEM>TEMPFILE.NR - temporary file where the nth part of the message is stored, nr being a number between 0 and n-1 (0 = first part after the headers, usually the body of the message)

RC is set to 10 if no Read window was previously specified as "active" with MAILREAD?.

NOTES

No filename is returned for the body of the message.

EXAMPLE

```
/* Enable result codes */
OPTIONS RESULTS

/* Silently decode the current message */
MAILREAD QUIET

/* Get info about the message, then close the window */
READINFO STEM ri.
READCLOSE

/* Display results */
DO i = 0 TO ri.filename.count-1
  SAY 'Information about part #'i+1
  SAY '  File name: 'ri.filename.i
  SAY '  File type: 'ri.filetype.i
  SAY '  File size: 'ri.filesize.i
  SAY '  Stored in: 'ri.tempfile.i
END
```

BUGS

The command used to blindly act upon the first Read window opened at any given time; this was changed in V2.4 to require the use of MAILREAD? to explicitly mark a window as "active".

SEE ALSO

MAILREAD?